


# Seasonal Runner

	Runner
	22 in. x 22 in.
Main	(1) 10.5 in. square
Accent	(1) Fat Quarter
Background	1/2 yard
Backing	7/8 yard
Binding	1/4 yard
Batting	30 in. x 30 in.



## Runner

22 in. x 22 in.

### From Main:

>> Cut (1) 10.5 in. square

### From the Accent:

>> Cut (8) 5.5 in. squares

### From the Background:

>> Cut (2) 7 in. squares

\* Subcut (4) 7 in. half-square triangles

>> Cut (4) 6.5 in. x 10.5 in rectangles

### From the Binding:

>> Cut (3) 2.5 in. x WOF strips

## Assembling the Runner

On the wrong side of the 5.5 in. accent squares, draw a diagonal line. Sewing on the diagonal line, stitch the 5.5 in. accent squares to the top corners of the 6.5 in. x 10.5 in. background squares. Trim 1/4 in. from the seam. Press towards background.



Next, sew (2) flying geese units from the previous step to the 10.5 in. main square. Then, sew a 7 in. HST to each side of the remaining flying geese units. Finally, sew each row together. Trim the HST, in necessary.

